


Créer une clé bootable System rescue CD

- manuel en français : <http://www.resoo.org/docs/systemrescuecd/Online-Manual-FR.htm>
- personnalisation : http://www.resoo.org/docs/systemrescuecd/Sysresccd-manual-fr_Comment_personnaliser_SystemRescueCd.htm

Personnalisation :



```
File Edit View Terminal Go Help
root@sysresccd /root % mount /dev/sda1 /mnt/custom
root@sysresccd /root % /usr/sbin/sysresccd-custom extract
/mnt/custom is mounted -> ok
there is enough estimated free space here (5860 MB) -> ok
root@sysresccd /root % /usr/sbin/sysresccd-custom squashfs
/mnt/custom is mounted -> ok
there is enough estimated free space here (4716 MB) -> ok
mksquashfs /mnt/custom/customcd/files/ /mnt/custom/customcd/isoroot/sysrcd.dat
Parallel mksquashfs: Using 1 processor
Creating 4.0 filesystem on /mnt/custom/customcd/isoroot/sysrcd.dat, block size 1
31072.
[=====] 22056/64348 34%
File Edit View Terminal Go Help
uucp (14)
root@sysresccd /root % /usr/sbin/sysresccd-custom setknop fr
/mnt/custom is mounted -> ok
Keymap to be loaded: fr
root@sysresccd /root % /usr/sbin/sysresccd-custom isogen my_srcd
/mnt/custom is mounted -> ok
there is enough estimated free space here (4426 MB) -> ok
Volume name of the CDROM: my_srcd
rmdir /mnt/custom/customcd/isoroot --> v
Final ISO image: /mnt/custom/customcd/isofile/sysresccd-20120316-0700.iso
root@sysresccd /root % cd /; umount /mnt/custom ; sync
root@sysresccd / %
root@sysresccd / %
```

Télécharger l'image iso

à l'adresse <http://www.sysresccd.org/Download>

Repérer la clé

Avec l'utilitaire de disque (dans Système/administration) :

- repérer la clé usb
- repérer son nom **/dev/sdx**
- démonter
- renommer en SYSRESCCD
- remonter

Le montage est donc : **/media/SYSRESCCD** pour **/dev/sdx**

créer le mbr et synchroniser pour écrire sur la clé :

```
sudo dd if=/usr/lib/syslinux/mbr.bin of=/dev/sdx
```

```
sync
```

<note tip>remplacer /dev/sdx par la valeur vue plus haut</note>

Copier les fichiers du cdrom

Monter l'image iso sur un répertoire à créer :

```
sudo mkdir /mnt/iso
sudo mount -o loop -t iso9660 /media/Disque/systemrescuecd-x86-1.6.0.iso
/mnt/iso
```

<note tip>remplacer par l'emplacement de l'image iso</note>

Copier les fichiers

```
cp -r /mnt/iso/* /media/SYSRESCCD/
rm -rf /media/SYSRESCCD/syslinux
mv /media/SYSRESCCD/isolinux/isolinux.cfg
/media/SYSRESCCD/isolinux/syslinux.cfg
mv /media/SYSRESCCD/isolinux/ /media/SYSRESCCD/syslinux
```

Rendre la clé amorçable

```
umount /media/SYSRESCCD
sudo syslinux /dev/sdx1
sync
```

<note tip>mettre la bonne référence /dev/dev/sdx1, sans oublier le numéro de partition</note>

From:

<https://nfrappe.fr/doc-0/> - **Documentation du Dr Nicolas Frappé**

Permanent link:

<https://nfrappe.fr/doc-0/doku.php?id=logiciel:os:windows:systemrescuecd:start>

Last update: **2022/08/13 22:14**

